

# Discord Bridge

The Discord bridge is no longer available for purchase. This documentation is for existing customers of the bridge only.

## Setup


First, you need to register a Discord application for your bridge. Discord applications can be registered and managed in the [Discord Developer Portal](#).

1. Click on the `New Application` button in the upper right corner.
2. Give it a name (visible when authorizing the bridge), read Discord's Terms and click `Create`.
3. Note the Client ID. It's required for the bridge.
4. Navigate to the `Bot` tab. The navigation can be found on the left.
5. Click `Add Bot`. You may also need to click `Yes, do it!` to confirm your action.
6. Note the Bot Token. It's required for the bridge.

## Authorize your account

Before authorizing your Discord App, you first need to grant your account the following rights:

1. Manage Webhooks
2. Manage Server



## Connect Discord server(s)

You need to authorize your Discord App to each Discord server you wish to bridge. Give the following URL to a Discord server admin, if you aren't the Discord server admin.

The authorization URL is

[https://discordapp.com/api/oauth2/authorize?client\\_id=YOUR\\_CLIENT\\_ID&scope=bot&permissions=607250432](https://discordapp.com/api/oauth2/authorize?client_id=YOUR_CLIENT_ID&scope=bot&permissions=607250432).


Replace `YOUR_CLIENT_ID` with your Client ID mentioned above.

# Usage

## Bridge a room

1. In a web browser, navigate to the Discord room you wish to bridge. The URL includes the server ID (also called guild ID) and the channel ID. The URL format is

`https://discord.com/channels/GUILD_ID/CHANNEL_ID`.



2. In a Matrix room you want to bridge, invite `@discord:example.ems.host` (replace the domain with the one of your homeserver).




3. Post the message `!discord bridge GUILD_ID CHANNEL_ID` after replacing the two placeholders.



## General on Discord

You created this room. This is the start of **General on Discord**.  
Add a topic to help people know what it is about.

 Invite to this room

-  EMS Support created and configured the room.
-  EMS Support invited discord.
-  discord joined the room.



**EMS Support**

`!discord bridge 786234150915014736 786234150915014739`




**discord**

18:19

I'm asking permission from the guild administrators to make this bridge.

4. A privileged Discord user will need to approve the bridge request by responding with `!matrix approve`



5. Messages from Discord are now bridged to Matrix and vice versa.



**discord**

I'm asking permission from the guild administrators to make this bridge.

---

I have bridged this room to your channel



ems joined the room.



18:23

**ems**

This is a message from Discord! 🗨️

## Unbridge

To unbridge a room post `!discord unbridge` in the Matrix room.

## Private Chats

Currently, private chats are not supported by the EMS Discord bridge.

---

Revision #9

Created 18 April 2022 14:19:53 by Karl Abbott

Updated 6 November 2024 12:28:49 by Kieran Mitchell Lane