

Configuring a microk8s Single Node Instance to Use a Network Proxy

Overview

If you are using the microk8s Single Node Installer and your site requires proxy access to get to the internet, making a few quick changes to your operating system configuration will enable our installer to access the resources it needs over the internet. This document discusses these changes.

Steps

We also cover the case where you need to use a proxy to access the internet. Please make sure that the following host variables are set:

Ubuntu Specific Directions

If your company's proxy is `http://corporate.proxy:3128`, you would edit `/etc/environment` and add the following lines:

```
HTTPS_PROXY=http://corporate.proxy:3128
HTTP_PROXY=http://corporate.proxy:3128
https_proxy=http://corporate.proxy:3128
http_proxy=http://corporate.proxy:3128
NO_PROXY=10.1.0.0/16,10.152.183.0/24,<node ip>,localhost,*.svc
no_proxy=10.1.0.0/16,10.152.183.0/24,<node ip>,localhost,*.svc
```

The IP Ranges specified to `NO_PROXY` and `no_proxy` are specific to the microk8s cluster and prevent microk8s traffic from going over the proxy. `<node ip>` needs to be replaced by the IP of your server

EL Specific Directions

Using the same example of having a company proxy at `http://corporate.proxy:3128`, you would edit `/etc/profile.d/http_proxy.sh` and add the following lines:

```
export HTTP_PROXY=http://corporate.proxy:3128
export HTTPS_PROXY=http://corporate.proxy:3128
export http_proxy=http://corporate.proxy:3128
export https_proxy=http://corporate.proxy:3128
export NO_PROXY=10.1.0.0/16,10.152.183.0/24,<node ip>,127.0.0.1,localhost,*.svc
export no_proxy=10.1.0.0/16,10.152.183.0/24,<node ip>,127.0.0.1,localhost,*.svc
```

The IP Ranges specified to `NO_PROXY` and `no_proxy` are specific to the microk8s cluster and prevent microk8s traffic from going over the proxy. `<node ip>` needs to be replaced by the IP of your server

In Conclusion

You will need to log out and back in for the environment variables to be re-read after setting them. If you already have microk8s running, you will need to issue:

```
microk8s.stop
microk8s.start
```

to have it reload the new environment variables.

If you need to use an authenticated proxy, then the URL schema for both EL and Ubuntu is as follows:

```
protocol:user:password@host:port
```

So if your proxy is `corporate.proxy` and listens on port 3128 without SSL and requires a username of `bob` and a password of `inmye1em3nt` then your url would be formatted:

```
http://bob:inmye1em3nt@corporate.proxy:3128
```

For further help with proxies, we suggest that you contact your proxy administrator or operating system vendor.

Revision #6

Created 28 July 2022 19:23:42 by Karl Abbott

Updated 6 November 2024 12:49:29 by Kieran Mitchell Lane